

- The process of setting this up requires two files from the Windows NT Resource Kit. These two files can also be found on itre's ftp site at **TIMS\_DM/resources/software/Service tools/**. The two files, **INSTSRV.EXE** and **SRVANY.EXE**, should be copied into the **c:\winnt** directory.
- This process requires editing the registry. **WARNING:** Using Registry Editor incorrectly can cause serious problems that may require you to reinstall your operating system. Microsoft cannot guarantee that problems resulting from the incorrect use of Registry Editor can be solved. Use Registry Editor at your own risk.

## Adding Eluise and Lockmanager as Services

Install Eluise, and Lockmanager as Windows NT/2000 services by typing the following command at a MS-DOS prompt:

- **instsrv Eluise c:\winnt\srwany.exe**
- **instsrv LockManager c:\winnt\srwany.exe**

After each command has been entered, you should see a message telling you that the service was added successfully. Now go to the Services Applet in the Control Panel and configure the newly added Services:

- **Startup Type:** Automatic.
- **Log On:** This Account,
- **Account:** Administrator (browse to it)
- **Password:** a valid password for the above account. Note: do not use an account where the password will be changing frequently as you would have to update these properties as often.

1. Start the Registry Editor by clicking on **Start > Run**, then type **regedt32**.
2. Browse to **HKEY\_LOCAL\_MACHINE\SYSTEM\CurrentControlSet\Services**

Path examples below assume Edulog.nt is installed on the **d:** drive. If the **ELT** folder resides on a different drive, you must substitute that drive in place of d: examples below.

### **A. Eluise**

1. Highlight **Eluise**, click on **Edit > Add Key**. Type in '**Parameters**' for the Key Name, and leave Class blank. Click OK.
2. Select the *Parameters* Key, click on **Edit > Add Value**. Type in '**Application**' for the Value Name, leave Data Type at REG\_SZ, and click OK. Under String specify the full path to the Eluise executable. For example; **d:\elt\exe\server\eluise.exe**.
3. Select the *Parameters* Key, click on **Edit > Add Value**. Type in '**AppParameters**' for the Value Name, leave Data Type at REG\_SZ, and click OK. Under String specify the full path to the Eluise configuration file. For example: **-f d:\elt\exe\server\eluise.cfg**.
4. To make the Eluise service dependent on the LockManager Service, Highlight Eluise, click on **Edit > Add Value**. Type in the value **DependOnService**. Change Data Type to REG\_MULTI\_SZ, then click OK. Under Data; type **LockManager**

## Running Eluise & Lock Manager as a Service

### *B. LockManager*

1. Highlight **LockManager**, click on **Edit > Add Key**. Type in '**Parameters**' for the Key Name, and leave Class blank. Click OK.
2. Select the *Parameters* Key, click on **Edit > Add Value**. Type in '**Application**' for the Value Name, leave Data Type at REG\_SZ, and click OK. Under String specify the full path to the Lock Manager executable. For example:  
**d:\elt\exe\server\lmw.exe**
3. Select the *Parameters* Key, click on **Edit > Add Value**. Type '**AppParameters**' for the Value Name, leave Data Type at REG\_SZ, and click OK. Under String specify the full path to the server directory. For example:  
**-mc SERVERNAME**

**Note:** To start the Services, either **reboot the server** or go to the **Services Applet** in Control Panel, highlight each Service, right-click and select **Start**.